

ALTERA®

**Quartus® II Installation &
Licensing for PCs**



QUARTUS® II

Quartus® II

Design Software

**Installation &
Licensing for PCs**



Altera Corporation
101 Innovation Drive
San Jose, CA 95134
(408) 544-7000
<http://www.altera.com>

Altera, the Altera logo, MAX, MAX+PLUS, MAX+PLUS II, NativeLink, Quartus, Quartus II, the Quartus II logo, and SignalTap are registered trademarks of Altera Corporation in the United States and other countries. APEX, ByteBlaster, ByteBlasterMV, Excalibur, LogicLock, MasterBlaster, Mercury, and Stratix are trademarks and/or service marks of Altera Corporation in the United States and other countries. Product design elements and mnemonics used by Altera Corporation are protected by copyright and/or trademark laws.

Altera Corporation acknowledges the trademarks and/or service marks of other organizations for their respective products or services mentioned in this document, specifically: Mentor Graphics and ModelSim are registered trademarks, and Exemplar Logic, LeonardoSpectrum, and ModelTechnology are trademarks of Mentor Graphics Corporation.

Altera reserves the right to make changes, without notice, in the devices or the device specifications identified in this document. Altera advises its customers to obtain the latest version of device specifications to verify, before placing orders, that the information being relied upon by the customer is current. Altera warrants performance of its semiconductor products to current specifications in accordance with Altera's standard warranty. Testing and other quality control techniques are used to the extent Altera deems such testing necessary to support this warranty. Unless mandated by government requirements, specific testing of all parameters of each device is not necessarily performed. In the absence of written agreement to the contrary, Altera assumes no liability for Altera applications assistance, customer's product design, or infringement of patents or copyrights of third parties by or arising from use of semiconductor devices described herein. Nor does Altera warrant or represent any patent right, copyright, or other intellectual property right of Altera covering or relating to any combination, machine, or process in which such semiconductor devices might be or are used.

Altera products are not authorized for use as critical components in life support devices or systems without the express written approval of the president of Altera Corporation. As used herein:

1. Life support devices or systems are devices or systems that (a) are intended for surgical implant into the body or (b) support or sustain life, and whose failure to perform, when properly used in accordance with instructions for use provided in the labeling, can be reasonably expected to result in a significant injury to the user.

2. A critical component is any component of a life support device or system whose failure to perform can be reasonably expected to cause the failure of the life support device or system, or to affect its safety or effectiveness.

Products mentioned in this document are covered by one or more of the following U.S. patents: RE37060; RE35977; 6453382; 6448820; 6442073; 6437650; 6433585; 6433579; 6429681; 6423572; 6417694; 6417692; 6417550; 6414518; 6414514; 6412812; 6411124; 6410379; 6408432; 6407576; 6407450; 6404225; 6401230; 6400635; 6400598; 6400290; 6396304; 6392954; 6392438; 6389558; 6384630; 6384629; 6384625; 6377069; 6373280; 6373278; 6369624; 6367056; 6367058; 6366498; 6366224; 6366121; 6366120; 6366119; 6365929; 6363505; 6362646; 6359469; 6359468; 6356110; 6356108; 6353552; 6353551; 6351152; 6351144; 6347061; 6346827; 6344989; 6344758; 6344755; 6342794; 6342792; 6340897; 6337578; 6335896; 6335636; 6335635; 6335634; 6326812; 6326807; 6323680; 6323677; 6321369; 6321367; 6320411; 6317860; 6317771; 6317367; 6314550; 6311309; 6301694; 6300794; 6300792; 6298319; 6297565; 6295230; 6294928; 6292116; 6292017; 6292016; 6288970; 6286114; 6285211; 6282122; 6281704; 6279145; 6278291; 6278288; 6275065; 6271729; 6271681; 6271680; 6271679; 6269020; 6268623; 6265926; 6265895; 6265746; 6263482; 6263400; 6262933; 6262595; 6259588; 6259272; 6259271; 6255850; 6255846; 6252422; 6252419; 6249149; 6249143; 6247155; 6247147; 6246270; 6246260; 6243304; 6243296; 6242946; 6242941; 6242772; 6239615; 6239613; 6239612; 6236597; 6236260; 6236237; 6236231; 6236094; 6232893; 6226201; 6225823; 6225822; 6222382; 6219785; 6219284; 6218876; 6218860; 6218859; 6215326; 6212668; 6208162; 6205579; 6204688; 6202185; 6201404; 6198303; 6195788; 6195772; 6192445; 6191998; 6191611; 6191608; 6187634; 6185725; 6184710; 6184707; 6184706; 6184705; 6184703; 6182247; 6182020; 6181162; 6181161; 6181160; 6181159; 6180425; 6177844; 6175952; 6173245; 6172900; 6169417; 6167364; 6166559; 6163195; 6163166; 6161211; 6160419; 6157212; 6157210; 6157208; 6154059; 6154055; 6151258; 6150840; 6147511; 6144573; 6137313; 6136407; 6134705; 6134173; 6134166; 6130555; 6130552; 6128692; 6128215; 6127865; 6127846; 6127844; 6127217; 6122720; 6122209; 6121790; 6120550; 6118720; 6118302; 6115312; 6114915; 6112200; 6110223; 6108239; 6107854; 6107825; 6107824; 6107822; 6107820; 6104208; 6102964; 6097211; 6094064; 6091258; 6091102; 6085317; 6084427; 6081449; 6080204; 6078521; 6076179; 6075380; 6072358; 6072332; 6069487; 6066960; 6064599; 6060903; 6058452; 6057707; 6052755; 6052327; 6052309; 6049225; 6049223; 6045252; 6043676; 6040712; 6038171; 6037829; 6034857; 6034540; 6034536; 6032159; 6031763; 6031391; 6029236; 6028809; 6028808; 6028787; 6026226; 6025737; 6023439; 6020760; 6020759; 6020758; 6018490; 6018476; 6014334; 6011744; 6011730; 6011406; 6005806; 6005379; 6002182; 5999016; 5999015; 5998295; 5998263; 5996039; 5986470; 5986465; 5983277; 5982195; 5978476; 5977793; 5977791; 5970255; 5969626; 5968161; 5966597; 5963565; 5963069; 5963051; 5963049; 5959891; 5953537; 5949991; 5949710; 5949250; 5949239; 5945870; 5943267; 5942914; 5940852; 5939790; 5936425; 5926036; 5925904; 5923567; 5915756; 5915017; 5914904; 5914509; 5909450; 5909375; 5909126; 5905675; 5904524; 5900743; 5898630; 5898628; 5898318; 5894228; 5893088; 5892683; 5883850; 5883526; 5880725; 5880597; 5880596; 5878250; 5875112; 5873131; 5872529; 5872463; 5870410; 5869980; 5869979; 5861760; 5859544; 5859542; 5850365; 5850152; 5850151; 5848005; 5847617; 5845385; 5844854; 5838628; 5838484; 5835998; 5834849; 5828229; 5825197; 5821787; 5821773; 5815721; 5815720; 5815024; 5815003; 5812479; 5812450; 5809281; 5809034; 5805516; 5802540; 5801541; 5796671; 5796267; 5793246; 5790469; 5787009; 5771264; 5768562; 5768372; 5767734; 5764583; 5764569; 5764080; 5764079; 5761099; 5760624; 5757207; 5757070; 5744991; 5744383; 5740110; 5732020; 5729495; 5717901; 5705939; 5699312; 5699022; 5696455; 5694058; 5693540; 5691653; 5689195; 5680061; 5672985; 5670895; 5668771; 5659717; 5656528; 5650734; 5649163; 5642262; 5642082; 5633830; 5633156; 5621312; 5614840; 5612642; 5608337; 5606273; 5606266; 5604453; 5598109; 5598108; 5592106; 5592102; 5590305; 5583749; 5581501; 5574893; 5572717; 5572148; 5572067; 5570040; 5567177; 5565793; 5563592; 5561757; 5557217; 5555214; 5550842; 5550782; 5548552; 5548228; 5543732; 5543730; 5541530; 5537341; 5537295; 5537057; 5525917; 5525827; 5523706; 5523247; 5517186; 5498995; 5495182; 5493526; 5493515; 5490266; 5488586; 5487143; 5486775; 5485103; 5485102; 5483178; 5477474; 5473266; 5463328; 5444394; 5438295; 5436575; 5436574; 5434514; 5432467; 5414132; 5399922; 5396452; 5384499; 5376844; 5375000; 5371422; 5359243; 5359242; 5353248; 5352940; 5350954; 5349255; 5341308; 5341048; 5341044; 5329487; 5317212; 5317210; 5315712; 5309046; 5301416; 5294975; 5285153; 5280203; 5274581; 5272368; 5268598; 5266037; 5260611; 5260610; 5258668; 5247478; 5247477; 5243233; 5241224; 5237219; 5220533; 5220214; 5200920; 5187392; 5166604; 5162680; 5144167; 5138576; 5128556; 5121006; 5111423; 5097208; 5091661; 5066873; 5045772; 4969121; 4930107; 4930098; 4930097; 4912342; 4903223; 4899070; 4899067; 4871930; 4864161; 4831573; 4829018; 4785423; 4774421; 4713792; 4677318; 4617479; 4609986; and certain foreign patents. Additional patents are pending.

Altera products are protected under numerous U.S. and foreign patents and pending applications, maskwork rights, and copyrights.

Copyright © 2002 Altera Corporation. All rights reserved.



I.S. EN ISO 9001

Contents

Documentation Conventions	1
Installing the Quartus II Software	3
System Requirements	3
Uninstalling Previous Versions of the Quartus or Quartus II Software.....	4
Running the Setup Program	5
Installing the TCP/IP Protocol.....	6
Licensing the Quartus II Software	8
Obtaining a License File.....	8
Modifying the License File.....	12
Setting Up a License Manager Server Under Windows NT, Windows 2000, or Windows XP	14
Installing a Sentinel Software Guard	16
Installing the Sentinel Driver	16
Installing the Software Guard	17
Starting the Quartus II Software	18
Specifying the License File.....	19
Specifying the License File Using the Quartus II Software	19
Specifying the License File Using the Windows NT, Windows 2000, or Windows XP System Control Panel	22
Specifying the License File in the Windows 98 autoexec.bat File	23
Additional PC Configuration Information	24
Registering as an Altera Fast Access User	25
Installing Programming Hardware	26
Installing the MasterBlaster Serial/USB Communications Cable.....	26
Installing the ByteBlaster II or ByteBlasterMV Parallel Port Download Cable	28
Installing the Altera ByteBlaster Driver for Windows NT	29
Installing the Altera ByteBlaster Driver for Windows 2000	30
Installing the Altera ByteBlaster Driver for Windows XP	31
Installing the ByteBlaster II or ByteBlasterMV Parallel Port Download Cable	32
Installing the Altera Programming Unit	34
Starting the Quartus II Tutorial	38
Using Quartus II Help.....	39
Getting Help on a Message	39

Using Context-Sensitive Help	40
Navigating Help	40
Using the Index Tab	40
Using the Search Tab	41
Using the Contents Tab	42
Printing Help Topics	42
Finding a Keyword in a Help Topic	43
Viewing a Glossary Definition	43
Quartus II File Organization	44
Contacting Altera	47
Technical Support	47
Product Information	48
Index	49

Documentation Conventions

The *Quartus II Installation & Licensing for PCs* manual uses the following conventions to make it easy for you to find and interpret information.

Terminology



The following terminology is used throughout the *Quartus II Installation & Licensing for PCs* manual:

Term:	Meaning:
“click”	Indicates a quick press and release of the left mouse button.
“double-click”	Indicates two clicks in rapid succession.
“choose”	Indicates that you need to use a mouse or key combination to start an action.
“select”	Indicates that you need to highlight text and/or objects or an option in a dialog box with a key combination or the mouse. A selection does not start an action. For example: Select Chain Description File , and click OK .
“turn on” / “turn off”	Indicates that you must click a check box to turn a function on or off.

Typographic Conventions

Quartus II documentation uses the following typographic conventions:

Visual Cue:	Meaning:
Bold Initial Capitals	Command names, dialog box titles, and button names are shown in bold, with initial capital letters. For example: Find Text command, Save As dialog box, and Start button.

Visual Cue:	Meaning:
bold	Directory names, project names, disk drive names, file names, file name extensions, software utility names, tab names, and options in dialog boxes are shown in bold. Examples: quartus directory, d: drive, license.dat file.
Initial Capitals	Keyboard keys, user-editable application window fields, and menu names are shown with initial capital letters. For example: Delete key, the Options menu.
“Subheading Title”	Subheadings within a manual section are enclosed in quotation marks. In manuals, titles of Help topics are also shown in quotation marks.
<i>Italic Initial Capitals</i>	Help categories, manual titles, section titles in manuals, and application note and brief names are shown in italics with initial capital letters. For example: <i>FLEXlm End Users Guide</i> .
<i>italics</i>	Variables are enclosed in angle brackets (< >) and shown in italics. For example: < <i>file name</i> >, < <i>CD-ROM drive</i> >.
Courier font	Anything that must be typed exactly as it appears is shown in Courier. For example: \quartus\bin\lmulti lmhostid.
■	Bullets are used in a list of items when the sequence of the items is not important.
✓	The checkmark indicates a procedure that consists of one step only.
	The hand points to information that requires special attention.
	The feet show you where to go for more information on a particular topic.
↵	Enter or return key.

Installing the Quartus II Software

This section describes the requirements and procedures for installing the Altera® Quartus® II software on PCs or compatible computers running Microsoft Windows NT version 4.0, Windows 98, Windows 2000, or Windows XP.

System Requirements

Your system must meet the following minimum requirements:

- Pentium II PC running at 400 MHz or faster
- Microsoft Windows NT version 4.0 (Service Pack 4 or later), Windows 98, Windows 2000, or Windows XP
- Microsoft Windows-compatible SVGA monitor
- CD-ROM drive
- One or more of the following ports:
 - Parallel port for use with the ByteBlaster™ II or ByteBlasterMV™ parallel port download cable
 - Serial port for use with the MasterBlaster™ communications cable
 - USB port for use with the MasterBlaster communications cable and the Altera Programming Unit (APU)(Windows 98, Windows 2000, and Windows XP only)
- Microsoft Internet Explorer software version 5.0 or later



Refer to the **readme.txt** file, which is located in the **quartus** directory on the Quartus II Design Software for PCs CD-ROM, for specific information about disk space and memory requirements in the current version of the Quartus II software.

In addition, the most current version of the *Quartus II Installation & Licensing for PCs* manual is available in Adobe Portable Document Format (PDF) from the Literature section of the Altera web site at <http://www.altera.com>, and may contain updated information about system requirements.

For the latest information on new features, device support, EDA interface support, and known issues and workarounds for the Quartus II software, refer to the *Quartus II Software Release Notes* document, which is available at http://www.altera.com/literature/rn/rn_qts.pdf.



You should have Microsoft Internet Explorer software version 5.0 or later installed, because portions of the Internet Explorer software are required to use the Quartus II online Help system. However, you do not need to make the Internet Explorer browser your default browser. You may need to configure the Internet Explorer software to work with your company network. For example, you may need to configure for a dial-up connection or for a proxy server. If necessary, you can download the Internet Explorer software from the Microsoft Internet Explorer web site at <http://www.microsoft.com/ie/>.

Uninstalling Previous Versions of the Quartus or Quartus II Software

If you have installed a previous version of the Quartus® or Quartus II software, Altera recommends that you uninstall that software before installing the new version of the software. However, it is not necessary to uninstall it.

To uninstall a previous version of the Quartus or Quartus II software:

- ✓ Choose **Programs > Altera > Quartus <version number> Uninstall, Repair or Modify** (Windows Start menu).

Running the Setup Program

The Quartus II software uses a Setup program for installation. Follow these steps to run the Setup program on your PC:



Installation on a PC running Windows NT 4.0, Windows 2000, or Windows XP requires that you have system administration (Administrator) privileges.

1. Insert the Quartus II Design Software for PCs CD-ROM into your CD-ROM drive. The Quartus II Install CD window appears automatically, offering several options. If the CD-ROM is in the drive, and the Setup program is not already running, start the Setup program manually by performing the following steps:
 - a. Choose **Run** (Windows Start menu).
 - b. In the **Run** dialog box, type `<CD-ROM drive>:\install`.
 - c. Click **OK**.
2. Click the **Install Quartus II Software** button to install the Quartus II software. The Setup program starts automatically and guides you through the installation process.

You can select a full installation or a custom installation. If you select a custom installation, you can select which device families you want to install, and you can also select whether you want to install EDA interfaces or tutorial files.



You must install support for the APEX™ 20K EP20K100E device if you want to complete the Basic or LogicLock™ Quartus II tutorial. In addition, you must install support for the Excalibur™ EPXA10 and Stratix™ EP1S25 devices if you want to complete the Excalibur and Stratix Advanced tutorial modules.

3. If you will run the Quartus II software using a network (multiuser) license, and not a node-locked (single-user) license, click the **Install FLEXlm Server** Control Panel button to install the FLEXlm License Manager software on the license server only.

The Quartus II software supports network license servers on PCs running Windows NT 4.0, Windows 2000, and Windows XP; on UNIX workstations running Solaris 2.6, 7, or 8, or HP-UX 11.0; and on PCs running Linux (Red Hat Linux 7.1). You do not need to install the FLEXlm License Manager software on network client PCs or on PCs running the Quartus II software using a node-locked (single-user) license. Refer to “Setting Up a License Manager Server Under Windows NT, Windows 2000, or Windows XP” on page 14 for more information about setting up the license manager server.

Installing the TCP/IP Protocol

If you do not already have the TCP/IP protocol installed on the PCs in your network, you must add it to your networking configuration. These instructions apply only to PCs running Windows 98 and Windows NT.

Follow these steps to install the TCP/IP protocol:

1. Close all other programs.
2. Insert your Windows operating system CD-ROM into your CD-ROM drive.
3. Choose **Settings > Control Panel** (Windows Start menu).
4. Double-click the **Network** icon in the Control Panel window.
5. In the **Network** dialog box, click the **Protocols** tab.
6. Click the **Add** button. The **Select Network Protocol** dialog box appears.
7. In the **Select Network Protocol** dialog box, select **TCP/IP Protocol** from the **Network Protocol** list.
8. Click **OK**.
9. In the **Windows <operating system> Setup** dialog box, make sure the directory path is **<CD-ROM drive>:\i386**.

10. Click **Continue**.
11. In the **Network** dialog box, click **Close** after all files have been copied.
12. When you are asked if it is OK to restart your computer, click **Yes**.



For information about installing the TCP/IP protocol on PCs running Windows 2000 or Windows XP, refer to your Windows 2000 or Windows XP documentation or to the Microsoft web site at <http://www.microsoft.com>.

Licensing the Quartus II Software

This section describes how to license the Quartus II software. To set up your license for the Quartus II software, you must perform the following steps, each of which is described in more detail in this section:

1. If necessary, obtain a license file. The Quartus II software requires a valid, unexpired **license.dat** license file for each server that supports a network (multiuser) license or for each node-locked (single-user) license. This same license file can also enable the additional Altera synthesis and simulation tools included with Altera software subscriptions, as well as the MAX+PLUS® II software.
2. If you are using a network license (FLOATPC, FLOATNET, or FLOATLNX), modify the license file.
3. If you are using a network license, set up and configure the FLEXlm license manager server.

or

If you are using a node-locked (FIXEDPC) license, install a Sentinel Software Guard.

4. Start the Quartus II software.
5. Specify the location of the license file.
6. Register as an Altera Fast Access user.

Obtaining a License File

You can obtain an ASCII license file, **license.dat**, from the Licensing section of the Altera web site at <http://www.altera.com> if you have the following information:

- Your Altera ID, which is a six-digit number that is provided when you purchase the Quartus II development system. This number is listed on the packing list that is shipped with the Quartus II software.
- Your serial number, which can be one of the following numbers:
 - If you have a network (multiuser) license version of the Quartus II software, the serial number is printed on the side of the Quartus II shipping box, and on the *Registration & License File Request Form*, which is also included with the Quartus II software package. This number begins with the letter G, and is followed by five digits (*Gxxxxx*).
 - If you have a node-locked (single-user) version of the Quartus II software, the serial number is the number on your Software Guard. This number begins with the letter T.
- Your Network Interface Card (NIC) number. To find your Windows NT server NIC number by using FLEXlm utilities, type the following command at a command prompt:

`<disk drive>:\quartus\bin\lmutil lmhostid ↵`



For information about additional methods of finding your NIC number, refer to the Solutions Database, which is available from the Support section of the Altera web site at <http://www.altera.com>. For complete information about using the FLEXlm utilities, you should refer to the *FLEXlm End Users Guide*, which is available at <http://www.globetrotter.com/TOC.htm>.

To obtain a license file, follow these steps:

1. Point your web browser to the Altera web site at <http://www.altera.com>.
2. Click the **Licensing** icon. The Altera Licensing Center page is displayed.
3. If you are using a node-locked (single-user) license, select the FIXEDPC license option.

or

If you are using a network (multiuser) license, select the FLOATPC, FLOATNET, or FLOATLNX license option.

4. Specify the requested information.



Altera recommends that you save any previous **license.dat** file in a temporary directory, in case you need to refer to it later.

5. You will receive an e-mail from Altera with a **license.dat** file attached, as well as the license file text. Altera recommends using the attached license file if you are using a node-locked (single-user) license. If you are using a network (multiuser) license, you may either use the attached license file, or copy the lines from the attached license file to an existing license file. If you are using the **license.dat** file with both the Quartus II software and the MAX+PLUS II software, Altera recommends that you save the **license.dat** file in a top-level directory named *<disk drive>:\flexlm*.

Figure 1 shows the Quartus II FEATURE line of a sample license file for a node-locked (single-user) license that uses a Software Guard.

Figure 1. Sample Node-Locked (Single-User) License File

Feature name	Daemon name	Version	Expiration date	Number of licenses requested	Authorization code
FEATURE	quartus	alterad	2002.07	permanent	uncounted
2BC9FE52E0F3 \					
HOSTID=GUARD_ID=T000002287 SIGN="1C66 DAC6 1DAB C886 727B 65DF \					
FAC2 B479 3E3C 656D 3561 E5D0 BBA3 C45C 4DDC 0F2F 68F5 4DF1 \					
6F63 7785 2F5D 1480 1B0A 70DE 2220 1952 DD CD 9F4D 6D61 A177"					

Figure 2 on page 11 shows a sample single-server network license file for a PC.

Figure 2. Sample Single-Server Network License File

```

SERVER alice 00c04f6bead6 1800
VENDOR alterad "<disk drive>:\quartus\bin\alterad.exe"
USE_SERVER
FEATURE quartus alterad 2002.07 permanent 5 7A496D25A602 SIGN="1C66 \
DAC6 1DAB C886 727B 65DF FAC2 B479 3E3C 656D 3561 E5D0 BBA3 \
C45C 4DDC 0F2F 68F5 4DF1 6F63 7785 2F5D 1480 1B0A 70DE 2220 \
1952 DDCD 9F4D 6D61 A177"
  
```

If you are using the Quartus II software with a node-locked (single-user) license, skip to “Installing a Sentinel Software Guard” on page 16.

The FLEXlm licensing scheme allows you to set up three redundant license servers to serve a network (multiuser) license. You can obtain a license file for redundant servers by performing the steps described earlier in this section for obtaining a license file. Figure 3 shows a sample redundant server license file.

Figure 3. Sample Redundant Server License File

```

SERVER alice 00c04f6bead6 1800
SERVER king 00c4fbbd170 1800
SERVER queen 00c4fbbd320 1800
VENDOR alterad "<disk drive>:\quartus\bin\alterad.exe"
USE_SERVER
FEATURE quartus alterad 2002.07 permanent 5 7A496D25A602 SIGN="1C66 \
DAC6 1DAB C886 727B 65DF FAC2 B479 3E3C 656D 3561 E5D0 BBA3 \
C45C 4DDC 0F2F 68F5 4DF1 6F63 7785 2F5D 1480 1B0A 70DE 2220 \
1952 DDCD 9F4D 6D61 A177"
  
```



For additional information about setting up and administering license servers, including setting up three redundant license servers, refer to the *FLEXlm End Users Guide*, which is available at <http://www.globetrotter.com/TOC.htm>.

Modifying the License File

The **license.dat** file must be modified before it can be used by the license server. See *Application Note 229 (Advanced Troubleshooting for Altera Software Licensing)* for a detailed description of the license file.



If you have a node-locked (single-user) license, you can skip this section and go to “Installing a Sentinel Software Guard” on page 16.

The first few lines of the license file are shown in the following example (your license file may not contain all the **VENDOR** entries, depending on which software you have enabled):

```
SERVER <host name> <8- or 12-character host or NIC ID> <port number>
VENDOR alterad "<path to daemon executable>"
VENDOR mgcld "<path to daemon executable>"
```

To modify the license file, follow these steps:

1. In the **license.dat** file, type the variables that are described in Table 1. The host or NIC ID will already be entered in the license file.

Table 1. Variables to Modify in the License File (license.dat) (Part 1 of 2)

Variable Name	Description	Directory
<host name>	The host name of the server; for example, <code>my_server</code> .	
<port number> (1)	The port number for the license manager service on the server; for example, 1800. The port number is optional and should be different from the port number for any other service on the machine.	

Table 1. Variables to Modify in the License File (license.dat) (Part 2 of 2)

Variable Name	Description	Directory
alterad "<path to daemon executable>" (1)(2)	Path to the Altera vendor daemon executable alterad .	\<Quartus II system directory>\bin\ alterad.exe
mgcld "<path to daemon executable>" (1)(2)(3)(4)	Path to the Mentor Graphics vendor daemon executable mgcld .	\<LeonardoSpectrum-Altera system directory>\ license\win32\mgcld.exe or \<ModelSim-Altera system directory>\ win32aolem\mgcld.exe
<p><i>Notes:</i></p> <p>(1) If you do not specify a port number in the license file, the FLEXlm License Manager will automatically choose a free port between 27000 and 27009. However, to prevent port number conflicts, you can specify a port number. If three redundant servers are being used, you must specify a port number. For PC-based license servers, Altera recommends that you specify a port number in the range of 27000-27009. However, you can use any unused port number between 0 and 64000.</p> <p>(2) In some network environments, the license server does not have an installation of the software tool(s) that provides the necessary vendor daemon (alterad or mgcld). In this case, copy the required daemon from another machine that does have an installation of the software. Find the file in the directory location specified. Save the file in a similarly named directory or any other location on the license server. Specify the daemon location on the license server in the license file.</p> <p>(3) If the path to the server has spaces in it, enclose the full path in quotation marks.</p> <p>(4) If you are not using a license file for the LeonardoSpectrum™-Altera or ModelSim®-Altera software, you may delete this line.</p>		

2. Save the license file with a **.dat** extension. Altera recommends that you name your license file **license.dat**.
3. Make sure the license file meets these guidelines:
 - The license file name must have a **.dat** extension. If your text editor adds **.txt** or another extension to the file name, such as **license.dat.txt**, you must rename the file to have only a **.dat** extension.
 - The license file must have a carriage return at the end of the last FEATURE line.
 - Any FEATURE line that wraps to a second or third line must contain a backslash (\) at the end of each line to indicate that it continues.



For additional information about modifying the license file for the Quartus II and MAX+PLUS II software and other EDA tools, refer to *Application Note 205 (Understanding Altera Software Licensing)* and *Application Note 229 (Advanced Troubleshooting for Altera Software Licensing)*, which are available from the Literature section of the Altera web site at <http://www.altera.com>.

Setting Up a License Manager Server Under Windows NT, Windows 2000, or Windows XP

This section provides instructions for setting up the FLEXlm license manager server on a PC running Windows NT 4.0, Windows 2000, or Windows XP. A system administrator should perform these steps to configure license servers after the Quartus II software is installed.



If you have a node-locked (single-user) license, you can skip this section and go to “Installing a Sentinel Software Guard” on page 16.

To configure a license server with the FLEXlm License Manager software, follow these steps:

1. If you have not already done so, modify the license file. The FLEXlm licensing scheme also allows you to set up three redundant license servers to serve a network (multiuser) license. You can obtain a license file for redundant servers by performing the steps described in “Obtaining a License File” on page 8. Figure 3 on page 11 shows a sample redundant server license file.
2. If you have not already done so, install the FLEXlm License Manager software from the Quartus II Design Software for PCs CD-ROM. Refer to “Running the Setup Program” on page 5 for information on installing the FLEXlm License Manager software.
3. Choose **Settings > Control Panel** (Windows Start menu).
4. Double-click the **FLEXlm License Manager** control panel icon.
5. To specify information about your license server, click the **Setup** tab.

6. Specify the **Service Name**. The default service name is **FLEXlm License Manager**, but because the license manager can administer both the Quartus II software and the Altera MAX+PLUS II software, Altera recommends that you change this name to **Altera License Manager** to avoid conflicts with other software programs that use the FLEXlm License Manager software.
7. Specify additional options on the **Setup** tab, always including the complete path names to the files you specify. The **lmgrd.exe** executable is located in the **<disk drive>:\<Windows directory>\system32** directory. Specifying the debug log file is optional.
8. To set up the Altera License Manager as a service, turn on **Use NT Services**. You can then use the **Services** control panel to adjust the starting and stopping behavior of the Altera License Manager. Setting up the Altera License Manager as a service allows licenses to be issued to other users after you have logged out of a Windows NT session.
9. If you want the Altera License Manager to start automatically when you start your PC, turn on **Start Server at Power-Up**.
10. Click the **Control** tab. This tab allows you to start, stop, and check the status of your license server.
11. In the **Control** tab, click **Start** to turn on your license server and launch the Altera License Manager as a background application.

After the license manager server has been set up in Windows NT, the license file must be specified for each client. Refer to "Specifying the License File" on page 19 for instructions on how to specify a license file.



For complete information about using the FLEXlm utilities to administer and troubleshoot the FLEXlm License Manager software, refer to the *FLEXlm End Users Guide*, which is available at <http://www.globetrotter.com/TOC.htm>.

Installing a Sentinel Software Guard

If your Quartus II development system uses a node-locked license and includes a Sentinel Software Guard, you must make sure the Sentinel driver is installed and then install the Software Guard before you can specify a license file.



If you have a network (multiuser) license, you can skip this section and go to “Starting the Quartus II Software” on page 18.

Installing the Sentinel Driver

The Sentinel driver is required for all Quartus II software systems running on Windows NT, Windows 2000, and Windows XP that use a Software Guard. The Sentinel driver is installed automatically with the Quartus II software.



1. Windows 98 systems require the Sentinel driver only if the software guard is on a parallel port other than LPT1.
2. Installing the Sentinel driver on a Windows NT system requires that you have system administration (Administrator) privileges.

If the Sentinel driver is not installed, you can install it by following these steps:

1. Choose **Run** (Windows Start menu).
2. In the **Run** dialog box, type the following command:

`<disk drive>:\quartus\drivers\setupx86.exe`
3. Click **OK**.
4. In the **Sentinel Driver Setup Program** window, choose **Install Sentinel Driver** (Functions menu).
5. In the **Sentinel Install** dialog box, specify the directory path to your `\quartus\drivers` directory.

6. Click **OK**.
7. Restart your computer at the prompt.

or

Open a command prompt window and type the following command:

```
net start sentinel ↵
```

Installing the Software Guard


To install the Software Guard on a PC, follow these steps:

1. Locate a parallel printer port (that is, an LPT port) on the computer. If you have a printer connected to this port, you must disconnect it temporarily.
2. Insert the 25-pin male connector end of the Software Guard into the 25-pin female connector of the parallel printer port, as shown in Figure 4 on page 18.



1. Do not connect disk drives that use the parallel port or any device, other than a printer or the ByteBlaster II or ByteBlasterMV download cable, to either end of the Software Guard. Disk drives can destroy a Software Guard by drawing more power than the guard is capable of handling.
2. Disconnect the Software Guard before using the parallel port to transfer data between computers using a data transfer program. Failure to do so can cause damage to the Software Guard.

Figure 4. Attaching the Software Guard to a PC



3. If necessary, reinsert the printer cable connector into the female connector of the Software Guard.

Starting the Quartus II Software

You can start the Quartus II software after installation is complete. In order to enable Quartus II features, however, you must specify the license file, either within the Quartus II software or outside of the Quartus II software. For information about how to specify your license file, refer to the next section, "Specifying the License File."

To start the Quartus II software:

- ✓ Choose **Programs > Altera > Quartus II <version number>** (Windows Start menu).

or

- ✓ Open a new command prompt window and type the following command:

```
<disk drive>:\quartus\bin\quartus ←
```


Specifying the License File

Once you have obtained a license file and set up a network license server (for multiuser licenses) or installed a Software Guard (for single-user licenses), you must specify the location of the license file for each user (or “client”). You can specify the license file with one of the following methods, which are described in more detail in this section:

- Specify the license file using the Quartus II software
- Specify the license file using the Windows NT, Windows 2000, or Windows XP **System** control panel
- Specify the license file in the Windows 98 **autoexec.bat** file



If you are using any of the Altera-provided synthesis and simulation software included with Altera software subscriptions, such as the Mentor Graphics® LeonardoSpectrum™ tool, or the Model Technology™ ModelSim®-Altera synthesis tool, and/or you are using the MAX+PLUS II software, you must specify the license file with either the System control panel or the **autoexec.bat** file.

Specifying the License File Using the Quartus II Software

You can specify the location of your license file from within the Quartus II software.



Specifying the license file from within the Quartus II software does not require system administration (Administrator) privileges.

To specify your license file within the Quartus II software, follow these steps:

1. If you have not already done so, start the Quartus II software, as described in “Starting the Quartus II Software” on page 18.
2. Choose **License Setup** (Tools menu). Figure 5 on page 21 shows the **License Setup** tab of the **Options** dialog box.

3. In the **License file** box, specify the full path name of your **license.dat** file. You can click **Browse (...)** to locate your **license.dat** file. Altera recommends that you store the **license.dat** file in a directory named **<disk drive>:\flexlm**.

You can also specify the location of the license file by typing a name of the format **<port>@<host>** instead of a license file path name, where **<host>** is the name of the server on which the license file is stored and **<port>** is the port listed in the **license.dat** file. Refer to Figure 2 on page 11 for a sample network license file to determine your port and server name, and see Table 1 on page 12 for more information about port numbers. If there is no port listed in the **license.dat** file, you can simply specify **@<host>**.




If you have more than one license file or server, separate the port and host specifications with semicolons (;), with no spaces between the names and numbers.

4. Click **OK**.

The **Licensed AMPP/MegaCore functions** list of the **License Setup** tab lists all of the AMPP and MegaCore functions that are available for the license.

Figure 5. License Setup Tab of the Options Dialog Box



Specifying the License File Using the Windows NT, Windows 2000, or Windows XP System Control Panel

You can specify the location of your license file from outside the Quartus II software by setting system variables in the Windows NT, Windows 2000, or Windows XP **System** Control Panel.



Specifying the license file in the **System** Control Panel requires that you have system administration (Administrator) privileges.

To specify the license file in the Windows NT **System** Control Panel, follow these steps:

1. Choose **Settings > Control Panel** (Windows Start menu).
2. Double-click the **System** icon in the Control Panel window.
3. In the **System Properties** dialog box, click the **Environment** tab.
4. Click the **System Variable** list to highlight it, and then in the **Variable** box, type `LM_LICENSE_FILE`.
5. In the **Value** box, type either `<disk drive>:\flexlm\license.dat` or a name of the format `<port>@<host>`, where `<host>` is the name of the server and `<port>` is the port listed in the `license.dat` file. Refer to Figure 2 on page 11 for a sample network license file to help you determine your port and server name. Refer also to Table 1 on page 12 for more information about port numbers. If there is no port listed in the `license.dat` file, you can simply specify `@<host>`.



If you have more than one license file or server, separate the port and host specifications with semicolons (;), with no spaces between the names and numbers.

6. Click **OK**.

To specify the license file in the Windows 2000 or Windows XP **System** Control Panel, follow these steps:

1. Choose **Settings > Control Panel** (Windows Start menu).
2. Double-click the **System** icon in the Control Panel window.

3. In the **System Properties** dialog box, click the **Advanced** tab.
4. In the **Advanced** tab, click **Environment Variables**.
5. Under **System Variables**, click **New**. The **New System Variable** dialog box is displayed.
6. In the **Variable Name** box, type `LM_LICENSE_FILE`.
7. In the **Variable Value** box, type either `<disk drive>:\flexlm\license.dat` or a name of the format `<port>@<host>`, where `<host>` is the name of the server and `<port>` is the port listed in the **license.dat** file. Refer to Figure 2 on page 11 for a sample network license file to help you determine your port and server name. Refer also to Table 1 on page 12 for more information about port numbers. If there is no port listed in the **license.dat** file, you can simply specify `@<host>`.



If you have more than one license file or server, separate the port and host specifications with semicolons (;), with no spaces between the names and numbers.

8. Click **OK**.

Specifying the License File in the Windows 98 **autoexec.bat** File

You can specify the location of your license file from outside the Quartus II software by adding an environment variable to your Windows 98 **autoexec.bat** file.



System administration (Administrator) privileges are not required to specify your license file in your Windows 98 PC's **autoexec.bat** file.

To specify the license file in the Windows 98 **autoexec.bat** file, follow these steps:

1. With a text editor, open your PC's **autoexec.bat** file.
2. Type the following environment variable on its own line in your **autoexec.bat** file:

```
set LM_LICENSE_FILE=<disk drive>:\flexlm\license.dat
```

or

```
set LM_LICENSE_FILE=<port>@<host>
```

where *<host>* is the name of the server and *<port>* is the port listed in the **license.dat** file. Refer to Figure 2 on page 11 for a sample network license file to help you determine your port and server name. Refer also to Table 1 on page 12 for more information about port numbers. If there is no port listed in the **license.dat** file, you can simply specify *@<host>*.



If you have more than one license file or server, separate the port and host specifications with semicolons (;), with no spaces between the names and numbers.

3. Save the **autoexec.bat** file.
4. Restart the PC.

Additional PC Configuration Information

If you receive the error message Can't start quartus_cmp server, starting attempt 1 of 3 when starting a compilation, simulation, or software build, increase the value of the environment variable **QUARTUS_PROCESS_TIMEOUT** from its default value of 100. If the environment variable does not exist, set it to an initial value of 100. You may have to increase the value until you no longer receive the error message.

Registering as an Altera Fast Access User

Your copy of the Quartus II software is registered at the time of purchase; however, in order to use the mySupport web site or the Download Center, Licensing Center, or Buy On-Line—Altera eStore sections of the Altera web site, you must also register as an Altera Fast Access user.

To register as an Altera Fast Access user, follow these steps:

1. Go to the mySupport web site:
 - ✓ To start your web browser and connect to the mySupport web site while running the Quartus II software, choose **Altera on the Web > Quartus II Home Page** (Help menu).
 - or*
 - ✓ Point your web browser to the mySupport web site at **<http://www.altera.com/mysupport>**.
2. Follow the instructions on the mySupport web site to register as a new Altera Fast Access user and create your Altera logon ID and password. If you are a current Altera subscription user, you will need the following information:
 - Your Altera ID, which is a six-digit number that is provided when you purchase the Quartus II design system. This number is listed on the packing list that is shipped with the Quartus II software.
 - Your License Type, which appears in the License type field in the **License Setup** dialog box (Tools menu) in the Quartus II software.
 - Your License ID, which appears in the **Host ID** field in the **License Setup** dialog box (Tools menu) in the Quartus II software.

If you are not a current Altera subscription user, you can still register as an Altera Fast Access user and create an Altera logon ID and password.

Installing Programming Hardware

This section describes how to install the MasterBlaster Serial/USB communications cable, the ByteBlaster II parallel port download cable, the ByteBlasterMV parallel port download cable, and the Altera Programming Unit (APU).

Installing the MasterBlaster Serial/USB Communications Cable

You can use the MasterBlaster Serial/USB communications cable to download configuration data to SRAM-based devices, such as APEX 20K and Mercury™ devices, and EEPROM-based devices, such as MAX® 3000 and MAX 7000 devices; to perform in-system programming of configuration devices, such as EPC2 and EPC16 devices; or to perform SignalTap® II logic analysis.

You can connect the MasterBlaster communications cable to an RS-232 serial port or, for Windows 98, Windows 2000, and Windows XP only, to a USB port. The MasterBlaster communications cable receives power from any one of the following sources:

- 5.0-V or 3.3-V circuit boards
- 5.0 V from the USB cable (Windows 98, Windows 2000, and Windows XP only)
- DC power supply, which is supplied with the MasterBlaster communications cable

To install and set up the MasterBlaster communications cable for device configuration or programming, follow these steps:


1. With either a standard RS-232 cable or a standard USB cable, connect one end of the cable to the MasterBlaster communications cable, and the other end of the cable to the appropriate port on the computer.



If you are using the MasterBlaster communications cable with the USB port, the Windows 98, Windows 2000, or Windows XP operating system prompts you to locate the USB driver **mbblaster.inf** file. The MasterBlaster driver is located in your `\quartus\drivers` directory.

2. Connect the 16-pin female header end of the communications cable to the 16-pin male MasterBlaster port, and the 10-pin female end of the communications cable to the 10-pin male header on the target printed circuit board. Figure 6 shows the MasterBlaster communications cable.

Figure 6. MasterBlaster Serial/USB Communications Cable



3. Open the Quartus II Programmer:
 - ✓ Choose **Programmer** (Tools menu).
 - or
 - ✓ Choose **New** (File menu). Click the **Other Files** tab, select **Chain Description File**, and click **OK**.

4. In the Programmer window, under **Programming Hardware**, click **Setup**. The **Hardware Setup** dialog box is displayed.
5. Click **Add Hardware**. The **Add Hardware** dialog box is displayed.
6. In the **Hardware type** list, select either **MasterBlaster (COM)** or **MasterBlaster (USB)**. The **USB** option is available only in Windows 98, Windows 2000, and Windows XP systems.
7. In the **Port** list, select the appropriate port.
8. If you are using a serial port, in the **Baud rate** list, select a baud rate appropriate for your computer.
9. Click **OK**.
10. In the **Hardware Setup** dialog box, click **Close**.



For more information about the MasterBlaster communications cable, refer to the *MasterBlaster Serial/USB Communications Cable Data Sheet*, which is available from the Literature section of the Altera web site at <http://www.altera.com>. For more information about SignalTap II logic analysis with the MasterBlaster communications cable, refer to “Selecting the Communications Cable for the SignalTap II Logic Analyzer” in Quartus II Help.

Installing the ByteBlaster II or ByteBlasterMV Parallel Port Download Cable

You can use the ByteBlaster II or ByteBlasterMV download cable to download configuration data to SRAM-based devices, such as APEX 20K and Mercury devices, and EEPROM-based devices, such as the MAX 3000 and MAX 7000 devices; to perform in-system programming of configuration devices, such as the EPC2 and EPC16 devices; or to perform SignalTap II logic analysis. You can also use the ByteBlaster II download cable to perform in-system programming of serial configuration devices, such as the EPCS1 and EPCS4 devices. You can connect the ByteBlaster II or ByteBlasterMV download cable directly to your PC's parallel port, or through an Altera Software Guard that is connected to the parallel port.

To install the ByteBlaster II or ByteBlasterMV download cable, you must perform the following steps, each of which are described in more detail in this section:

1. Install the Altera ByteBlaster driver.
2. Install the ByteBlaster II or ByteBlasterMV download cable.

Installing the Altera ByteBlaster Driver for Windows NT

The Altera ByteBlaster driver is required for PCs running Windows NT 4.0 that use the ByteBlaster II or ByteBlasterMV download cable. You must install the Altera ByteBlaster driver separately from the Quartus II software.



1. You do not need to install the ByteBlaster II or ByteBlasterMV download cable before installing the Altera ByteBlaster driver.
2. Installing the Altera ByteBlaster driver requires that you have system administration (Administrator) privileges.

To install the Altera ByteBlaster driver for Windows NT, follow these steps:

1. Choose **Settings > Control Panel** (Windows Start menu).
2. In the Control Panel window, double-click the **Multimedia** icon.
3. In the **Multimedia Properties** dialog box, click the **Devices** tab, and click **Add**.
4. In the **List of Drivers** list, select **Unlisted or Updated Driver** and click **OK**.
5. In the **Install Driver** dialog box, type `<disk drive>:\quartus\drivers` or select the name with **Browse (...)** to specify the Quartus II software **drivers** directory.
6. Click **OK**.
7. In the **Add Unlisted or Updated Driver** dialog box, select **Altera ByteBlaster**.

8. To restart your computer, click **Restart Now**.

Installing the Altera ByteBlaster Driver for Windows 2000

The Altera ByteBlaster driver is required for PCs running Windows 2000 that use the ByteBlaster II or ByteBlasterMV download cable. You must install the Altera ByteBlaster driver separately from the Quartus II software.



1. You do not need to install the ByteBlaster II or ByteBlasterMV download cable before installing the Altera ByteBlaster driver.
2. Installing the Altera ByteBlaster driver requires that you have system administration (Administrator) privileges.

To install the Altera ByteBlaster driver for Windows 2000, follow these steps:

1. Choose **Settings > Control Panel** (Windows Start menu).
2. In the **Control Panel** window, double-click the **Add/Remove Hardware** icon and click **Next**.
3. In the **Choose a Hardware Task** page of the **Add/Remove Hardware** wizard, select **Add/Troubleshoot a device** and click **Next**.
4. In the **Choose a Hardware Device** page, select **Add a new device** and click **Next**.
5. In the **Find New Hardware** page, select **No, I want to select the hardware from a list** and click **Next**.
6. In the **Hardware Type** page, select **Sound, video and game controllers** and click **Next**.
7. In the **Select a Device Driver** page, select **Have disk**.
8. Specify the full directory path to the `\quartus\drivers\win2000` directory with **Browse (...)**, and click **OK**.
9. In the **Digital Signature Not Found** page, click **Yes**.

10. In the **Select a Device Driver** page, select either **ByteBlaster II** or **ByteBlasterMV**, and click **Next**.
11. In the **Start Hardware Installation** page, click **Next**.
12. In the **Digital Signature Not Found** page, click **Yes**.
13. In the **Completing the Add/Remove Hardware Wizard** page, click **Finish**.
14. To restart your computer, click **Restart Now**.

Installing the Altera ByteBlaster Driver for Windows XP

The Altera ByteBlaster driver is required for PCs running Windows XP that use the ByteBlaster II or ByteBlasterMV download cable. You must install the Altera ByteBlaster driver separately from the Quartus II software.



1. You do not need to install the ByteBlaster II or ByteBlasterMV download cable before installing the Altera ByteBlaster driver.
2. Installing the Altera ByteBlaster driver requires that you have system administration (Administrator) privileges.

To install the Altera ByteBlaster driver for Windows XP, follow these steps:

1. Choose **Control Panel** (Windows Start menu).
2. Click the **Switch to Classic View** link.
3. In the **Control Panel** window, double-click **Add Hardware** and click **Next**. The **Add/Remove Hardware Wizard** dialog box appears.
4. Select **Yes, I have already connected the hardware** and click **Next**.
5. In the **Installed hardware** list, select **Add a new hardware device** and click **Next**.
6. Select **Install the hardware that I manually select from a list (Advanced)** and click **Next**.

7. Select **Sound, video and game controllers** and click **Next**.
8. Select **Have disk**.
9. Specify the full directory path to the `\quartus\drivers\win2000` directory with **Browse (...)**, and click **OK**.
10. In the **Digital Signature Not Found** page, click **Yes**. A software installation warning appears.
11. Click **Continue Anyway**.
12. Select **Altera ByteBlaster** and click **Next**. A hardware installation warning appears.
13. Click **Continue Anyway**.
14. Click **Finish**.
15. When prompted to restart your computer, click **Yes**.

Installing the ByteBlaster II or ByteBlasterMV Parallel Port Download Cable


To install and set up the ByteBlaster II or ByteBlasterMV parallel port download cable for device configuration or programming, follow these steps:

1. Attach the ByteBlaster II or ByteBlasterMV download cable to a parallel port on your PC and insert the 10-pin female plug into the prototype system containing the target device, as shown in Figure 7 on page 33.



The board must supply power to the ByteBlaster II or ByteBlasterMV download cable.

Figure 7. ByteBlaster II or ByteBlasterMV Parallel Port Download Cable



2. Open the Quartus II Programmer:
 - ✓ Choose **Programmer** (Tools menu).
 - or*
 - ✓ Choose **New** (File menu). Click the **Other Files** tab, select **Chain Description File**, and click **OK**.
3. In the Programmer window, under **Programming Hardware**, click **Setup**. The **Hardware Setup** dialog box is displayed.
4. Click **Add Hardware**. The **Add Hardware** dialog box is displayed.
5. In the **Hardware type** list, select **ByteBlaster II** or **ByteBlasterMV**.
6. In the **Port** list, select the appropriate port.
7. Click **OK**.



For more information about the ByteBlaster II or ByteBlasterMV parallel port download cable, refer to the *ByteBlaster II Parallel Port Download Cable Data Sheet* or *ByteBlasterMV Parallel Port Download Cable Data Sheet*, respectively, which are available from the Literature section of the Altera web site at **<http://www.altera.com>**.


For more information about SignalTap II logic analysis with the ByteBlaster II or ByteBlasterMV download cable, refer to “Selecting the Communications Cable for the SignalTap II Logic Analyzer” in Quartus II Help.

Installing the Altera Programming Unit

The Altera Programming Unit (APU) consists of a base unit and one or more adapters that program Altera devices. The APU is supported for Windows 98, Windows 2000, and Windows XP only, and is connected to a PC using a USB port.

Figure 8 shows an assembled PL-APU Altera Programming Unit, adapter, and cables.


Figure 8. Altera Programming Unit (APU)



To install the APU, follow these steps:

1. Connect the APU to the USB port on your PC with the USB cable.
2. Connect the universal input power supply from the APU to the appropriate power adapter for your country and connect the power adapter to a power source.
3. Install the adapter by sliding the two tabs at the top of the adapter into the slots provided on the base unit as shown in Figure 9. Be sure to use the appropriate adapter for the device you want to program.
4. Carefully lower and align the other end of the adapter, so that the connection in the adapter is inserted into the socket on the base unit. Press down firmly.

Figure 9. Installing the Adapter




5. Open the Quartus II Programmer:
 - ✓ Choose **Programmer** (Tools menu).
 - or*
 - ✓ Choose **New** (File menu). Click the **Other Files** tab, select **Chain Description File**, and click **OK**.
6. In the Programmer window, under **Programming Hardware**, click **Setup**. The **Hardware Setup** dialog box is displayed.
7. Click **Add Hardware**. The **Add Hardware** dialog box is displayed.
8. In the **Hardware type** list, select **APU (USB)**. The Windows 98, Windows 2000, or Windows XP operating system prompts you to locate the USB driver, which is located in the `\quartus\drivers` directory.
9. Click **OK**.

To release an adapter from the base unit:

1. Press down on the front of the base unit, while holding down the other end of the adapter. See Figure 10 on page 37.
2. Lift out the adapter.

Figure 10. Releasing the Adapter



Starting the Quartus II Tutorial

The online tutorial introduces you to the features of the Quartus II design software. It shows you how to create and process your own logic designs quickly and easily. The modular design of the Basic and Advanced tutorials allows you to choose the areas of the Quartus II software that you want to learn about:

- The Basic tutorial guides you through the steps required to create, perform timing analysis on, simulate, and program a sample finite impulse response (FIR) filter design, called **fir_filter**.
- The Advanced tutorial builds on the training in the Basic tutorial, focusing on the LogicLock feature and Excalibur and Stratix device features.

To start the Quartus II tutorial after you have successfully installed the Quartus II software:

- ✓ Choose **Tutorial** (Help menu).

After you start the tutorial, the Quartus II window resizes to allow you to view the Tutorial window and the Quartus II software simultaneously.



1. You must have installed support for the APEX 20K EP20K100E device if you want to complete the Basic or LogicLock tutorial. In addition, you must have installed support for the Excalibur EPXA10 and Stratix EP1S25 devices if you want to complete the Excalibur and Stratix Advanced tutorial modules. If you did not install support for these devices, refer to “Running the Setup Program” on page 5.
2. The tutorial is designed for display online. However, if you want to print one or more of the tutorial modules, click the Printing Options button located at the beginning of each module and then click the link to open the appropriate printable version.

Using Quartus II Help

The Quartus II software includes a platform-independent Help system that provides comprehensive documentation for the Quartus II software and more details about the specific messages generated by the Quartus II software. You can view Help in one of the following ways:

- Press F1 from a highlighted menu command or active dialog box for context-sensitive help.
- Choose **Index** (Help menu) to view the **Index** tab. The Index lets you search for and display all Help topics related to a keyword or phrase.
- Choose **Contents** (Help menu) to view the **Contents** tab. The Contents outlines the design flow and groups related topics into folders, but does not list all the topics in Quartus II Help.
- Choose **Search** (Help menu) to perform a search with the **Search** tab. The Search finds a maximum of 500 topics containing the search keyword.
- Choose **Messages** (Help menu) to view the Messages list. The Messages list provides an alphabetical list of all messages and offers detailed Help on each message.
- Choose **Glossary** (Help menu) to view the Glossary list. The Glossary list provides definitions to key terminology in the Quartus II software.



Refer to “Help Menu Commands” and “Using Quartus II Help Effectively” in Quartus II Help for more information.

Getting Help on a Message

To view Help on an individual message, follow these steps:

1. In the **Processing** tab of the messages window, select the message on which you want to receive Help.
2. Choose **Help** (right button pop-up menu).

To view the entire alphabetical list of messages:

- ✓ Choose **Messages** (Help menu).

or


- ✓ Choose **Contents** (Help menu), and select **Messages List** from the end of the Contents.

Using Context-Sensitive Help

To view context-sensitive help for a specific item:

- ✓ Press F1 from a highlighted menu command or active dialog box for context-sensitive help.

or

- ✓ Press Shift+F1 or choose the **Context-Sensitive Help** button  on the toolbar. The pointer turns into a Help pointer. You can then point to a menu command or active window and click for context-sensitive help.

Navigating Help

The Help window includes a **Contents** tab, **Index** tab, and **Search** tab that can help you navigate through thousands of Help topics.

Using the Index Tab

To find and display a Help topic using the Index, follow these steps:

1. Choose **Index** (Help menu) or, if the Help window is already open, click the **Index** tab.

2. Type the entry you want to find in the **Type in the keyword to find** box.
3. In the list of keywords, select the entry or sub-entry.



If the entry you are looking for refers to a cross-reference entry in parentheses that is preceded with **See** or **See also**, you can type that entry in the **Type in the keyword to find** box to locate additional topics.

4. To open the topic, click **Display** or double-click the entry.

Using the Search Tab

To search all topics in Quartus II Help for specific keywords, follow these steps:

1. Choose **Search** (Help menu) or, if the Help window is already open, click the **Search** tab.
2. Type the keyword or keywords that you want to find:
 - To find topics with adjacent keywords, type the keywords in double quotation marks. For example, “this and that” finds topics that contain the exact phrase “this and that.”
 - To find topics that contain the keywords, type the keywords without double quotation marks. For example, this and that finds topics that contain any combination of the words “this,” “and,” and “that.”
3. If necessary to narrow your search, select **AND**, **OR**, **NEAR**, or **NOT** from the list.
4. If necessary, turn on **Search previous results**, **Match similar words**, or **Search titles only**.
5. Click **List Topics**.
6. Select the topic you want to display.
7. Click **Display**.

Using the Contents Tab

To view groups of related topics, follow these steps:

1. Choose **Contents** (Help menu) or, if the Help window is already open, click the **Contents** tab.
2. Select the Help folder topic you want to view.
3. Click the + icon to expand the folder and view the names of individual Help topics.
4. Select the topic you want to display.

Printing Help Topics

To print Quartus II Help topics from the **Contents** tab, follow these steps:

1. In the **Contents** tab, select the Help folder or Help topic that you want to print.
2. Choose **Print** (right button pop-up menu).

or

Click the **Print** button  on the toolbar.

3. Select the appropriate print option:
 - To print the selected topic, select **Print the selected topic**.
 - To print the selected folder and all the topics in the folder, select **Print the selected heading and all subtopics**.
4. Click **OK**.



You can also use the **Print** command or **Print** button to print any individual Help topic you are viewing.

Finding a Keyword in a Help Topic

To search for a keyword in an open Quartus II Help topic, follow these steps:

1. To open the **Find** dialog box, press Ctrl + F.
2. In the **Find what** box, type the search text.
3. If necessary, turn on one or both of the following options:
 - **Match whole word only**
 - **Match case**
4. In the **Direction** list, select a search direction.
5. Click **Find Next**.
6. If necessary, click **Find Next** again to find the next instance of the search text.
7. To end the search, click **Cancel**.

Viewing a Glossary Definition

To view the alphabetical glossary list:

- ✓ Choose **Glossary** (Help menu).

or

- ✓ Choose **Contents** (Help menu), and select **Glossary List** from the end of the Contents.

Quartus II File Organization

During the Quartus II software installation, two top-level directories are created: **quartus** and **qdesigns**.

- The **quartus** directory contains system software and data files and includes the subdirectories described in Tables 2 through 4.
- The **qdesigns** directory contains tutorial and sample files and includes the subdirectories described in Table 5.

The main **quartus** directory includes the subdirectories described in Table 2.

Table 2. Quartus II System Directory (quartus) Structure

Directory	Description
.bin	Contains the executable software program files.
.drivers	Contains drivers, including the following drivers: <ul style="list-style-type: none"> ■ Altera ByteBlaster driver, which is required to use the ByteBlaster II or ByteBlasterMV download cable with Windows NT, Windows 2000, and Windows XP ■ MasterBlaster USB driver, which is required to use the MasterBlaster communications cable with USB for Windows 98, Windows 2000, and Windows XP ■ APU USB driver, which is required to use the APU with Windows 98, Windows 2000, and Windows XP ■ Sentinel driver, which is required to use the Sentinel Software Guard with node-locked (single-user) licenses for Windows NT
.eda	Contains libraries for use with other EDA tools. Refer to Table 3 for information on the subdirectories of this directory.
.libraries	Contains the Quartus II software directory for “self-contained” libraries. Refer to Table 4 for information on the subdirectories of this directory.
.lmf	Contains Library Mapping Files (.lmf).

The `\quartus\eda` directory includes the subdirectories described in Table 3.

Table 3. Quartus II EDA Directory (eda) Structure

Directory	Description
<code>\cadence</code>	Contains technology libraries for Cadence EDA tools.
<code>\ibis</code>	Contains input files that allow the Quartus II software to generate design-specific IBIS Output Files for EDA tools.
<code>\mentor</code>	Contains technology libraries for Mentor Graphics EDA tools.
<code>\sim_lib</code>	Contains VHDL and Verilog HDL simulation libraries that are compatible with EDA tools from other vendors.
<code>\synopsys</code>	Contains technology libraries for Synopsys EDA tools.
<code>\innoveda</code>	Contains technology libraries for Innoveda EDA tools.
<code>\fv_lib</code>	Contains formal verification model libraries.

The `\quartus\libraries` directory includes the subdirectories described in Table 4.

Table 4. Quartus II Library Directory (libraries) Structure (Part 1 of 2)

Directory	Description
<code>\megafunctions</code>	Contains megafunctions, including Library of Parameterized Modules (LPM) functions, corresponding Include Files (<code>.inc</code>) that contain their AHDL Function Prototypes, and corresponding Block Symbol Files (<code>.bsf</code>).
<code>\others</code>	Contains libraries of logic functions that provide compatibility between the Quartus II software and the MAX+PLUS II software.
<code>\primitives</code>	Contains Block Symbol Files (<code>.bsf</code>) for Quartus II primitives.
<code>\software</code>	Contains the bootloader library file that generates flash programming files with the Quartus II software and the ADS Toolset.
<code>\tcl_scripts</code>	Contains Tcl scripts to perform tasks in the Quartus II software and other EDA software.
<code>\vhdl87</code>	Contains the library of IEEE std. 1076–1987 VHDL packages.
<code>\vhdl93</code>	Contains the library of IEEE std. 1076–1993 VHDL packages.

Table 4. Quartus II Library Directory (libraries) Structure (Part 2 of 2)

Directory	Description
.\verific_vhdl87	Contains files to support VHDL design processing.
.\verific_vhdl93	Contains files to support VHDL design processing.

The \quartus\qdesigns work directory includes the subdirectories described in Table 5.

Table 5. Quartus II Work Directory (qdesigns) Structure

Directory	Description
.\tutorial	Contains the completed project and design files for the Basic tutorial. This directory includes a readme.txt file that contains important information about the tutorial.
.\fir_filter	Directory in which you should create the fir_filter project if you are completing the Design Entry tutorial module. Use this directory to prevent accidental changes to the original design files in the \qdesigns\tutorial directory.
.\fir_filter\compile	Contains the compile_fir_filter project for use when completing the Compilation tutorial module independently or nonsequentially.
.\fir_filter\timing	Contains the timing_fir_filter project for use when completing the Timing Analysis tutorial module independently or nonsequentially.
.\fir_filter\simulate	Contains the simulate_fir_filter project for use when completing the Simulation tutorial module independently or nonsequentially.
.\fir_filter\program	Contains the program_fir_filter project for use when completing the Programming tutorial module independently or nonsequentially.
.\excalibur	Contains the arm_tutorial project for use when completing the Excalibur tutorial module.
.\excalibur\arm_c	Contains the arm_tutorial.c and associated Assembly Files (.s) for use when completing the Excalibur tutorial module.
.\logiclock\largefilter	Contains the largefilter project for use when completing the LogicLock tutorial module.
.\logiclock\filter	Contains the filter project for use when completing the LogicLock tutorial module.
.\stratix	Contains the stratix_tutorial project for use when completing the Stratix tutorial module.

Contacting Altera

You can contact Altera for technical support and product information.

Technical Support

If you need technical support, you can visit the Altera web site or the mySupport web site, or you can call or fax the Altera Applications Department.



You must register as an Altera Fast Access user to use the mySupport web site, or the Download Center, Licensing Center, or Buy On-Line–Altera eStore sections of the Altera web site. For more information, refer to “Registering as an Altera Fast Access User” on page 25.

Altera web site:

<http://www.altera.com>

Includes the Solutions Database, which is available from the Support Center section of the Altera web site.

mySupport web site:

<http://www.altera.com/mysupport>

or choose **Altera on the Web > Quartus II Home Page** (Help menu) in the Quartus II software. This web site allows you to submit, view, and update technical support service requests.

Telephone:

(800) 800-EPLD

(7:00 a.m. to 5:00 p.m. Pacific time, M–F)

You will need your 6-digit Altera ID to access the hotline.

(408) 544-7000

(7:00 a.m. to 5:00 p.m. Pacific time, M–F)

Fax:

(408) 544-6401

Product Information

If you need the latest Altera product information or literature, go to the Literature section of the Altera web site at <http://www.altera.com>.



Go to “Contacting Altera” in Quartus II Help for complete information on Altera technical support services.

Index

A

- Altera Fast Access 25, 47
- Altera License Manager 15
- Altera on the Web** command 25
- Altera Programming Unit, installing 34
- Altera web site 47
- Altera, contacting 47
- APU, installing 34

B

- ByteBlaster II cable
 - installing hardware 32
 - installing Windows 2000 driver 30
 - installing Windows NT driver 29
 - installing Windows XP driver 31
- ByteBlasterMV cable
 - installing hardware 32
 - installing Windows 2000 driver 30
 - installing Windows NT driver 29
 - installing Windows XP driver 31

C

- CD-ROM
 - installing FLEXlm software for PCs 5
 - installing Quartus II software 3
- contacting Altera 47

D

- directory structure 44
- documentation conventions 1
- drivers
 - installing ByteBlaster 29, 30, 31
 - installing MasterBlaster 26
 - installing Sentinel 16
 - installing USB 26

E

- EDA interfaces, installation 5

F

- FLEXlm software
 - FLEXlm manual web site 9, 12
 - installing for PCs 5
 - setting up a license manager 15

H

- Hardware Setup** dialog box 28, 33, 36
- Help

- Contents** tab 42
 - context-sensitive 40
 - finding keywords in 43
- Index** tab 40
 - on messages 39
 - printing 42
- Search** tab 41
 - using 39
 - viewing glossary list 43

I

- installation
 - Altera Programming Unit 26
 - ByteBlaster driver 29, 30, 31
 - ByteBlaster II cable 28
 - ByteBlasterMV cable 28
 - EDA interfaces 5
 - FLEXlm software 5
 - MasterBlaster cable 26
 - Quartus II software 3
 - Sentinel driver 16
 - USB driver 26

L

LeonardoSpectrum software, specifying
 license file 19
license file
 license.dat file 8
 modifying 12
 obtaining 8
 specifying 19
license server configuration, setting up on
 Windows NT, Windows 2000, or
 Windows XP 14
license.dat file 8
lmhostid utility 9
lmutil utility 9

M

MasterBlaster cable, installing 26
MAX+PLUS II software, using with
 Quartus II license file 10, 19
messages, getting Help on 39
Microsoft Internet Explorer software 4
ModelSim-Altera synthesis software,
 specifying license file 19
mySupport web site 25, 47

O

Open Programmer command 27, 33, 36
Options command 19

P

parallel port 3
Pentium II 3
port number, specifying 20
product information 47, 48
Programmer window 28, 33

Q

qdesigns directory 44
quartus directory 44
Quartus II software, starting 18

R

readme.txt file 3
registering as an Altera Fast Access user 25
Registration & License File Request
 Form 9

S

Sentinel driver, installing 16
serial number 9
serial port 3
Setup program, running 5
SignalTap II logic analyzer 26, 28
Software Guard
 connecting ByteBlaster II or
 ByteBlasterMV cable
 through 28
 installing Sentinel driver 16
 serial number 9
system requirements 3

T

TCP/IP protocol 6
technical support 47
tutorial, starting 38

U


uninstalling Quartus II software 4
USB port 3

W

Windows 98
 installing Quartus II software 5
 specifying license file 19
 TCP/IP Protocol 6
Windows NT, Windows 2000, and
 Windows XP
 installing Quartus II software 5
 setting up license server 14
 specifying license file 19
 TCP/IP Protocol 6

Notes

Notes





Altera Corporation
101 Innovation Drive
San Jose, California 95134 USA
<http://www.altera.com>

P25-04731-08